Sunshine

ReenigneArcher

ABOUT

1	Over	
	1.1	About
	1.2	Integrations
	1.3	Support
	1.4	Downloads
2	Insta	llation 5
	2.1	Binaries
	2.2	Docker
	2.3	Linux
	2.4	MacOS
	2.5	Windows
3	Dock	er 9
	3.1	Using docker run
	3.2	Using docker-compose
	3.3	Parameters
	3.3	
4		d Party Packages
	4.1	AUR (Arch Linux User Repository)
	4.2	Chocolatey
	4.3	Scoop
	4.4	Legacy GitHub Repo
5	Usag	
	5.1	Network
	5.2	Arguments
	5.3	Setup
	5.4	Shortcuts
	5.5	Application List
	5.6	Considerations
6	Adva	anced Usage
	6.1	Configuration
	6.2	General
	6.3	Controls
	6.4	Display
	6.5	Audio
	6.6	Network
	6.7	Encoding
	6.8	Advanced
	0.0	Advanced

7	General	39
8	Linux	41
9	MacOS	43
10	Windows	45
11	Build	47
	11.1 Building Locally	47
	11.2 Remote Build	47
12	Linux	49
	12.1 Requirements	49
	12.2 Build	53
	12.3 Dockerfile Builds	54
13	MacOS	55
	13.1 Requirements	55
	13.2 Build	55
14	Windows	57
	14.1 Requirements	57
	14.2 Build	57
15	Contributing	59
16	Localization	61
	16.1 CrowdIn	62
	16.2 Extraction	62
17	Testing	65
	17.1 Clang Format	65
	17.2 Sphinx	65
	17.3 Unit Testing	66

SunshineStream has this documentation hosted on Read the Docs.

ABOUT 1

2 ABOUT

CHAPTER

ONE

OVERVIEW

1.1 About

Sunshine is a Game stream host for Moonlight. It is an open source version of GeForce Experience (GFE).

These are the advantages of Sunshine over GFE.

- FOSS (Free and Open Source Software)
- Multi-platform
 - Linux (deb, rpm, and AppImage packages)
 - MacOS (Portfile)
 - Windows (portable binary)
- Pair over web ui
- Supports AMD and Nvidia GPUs for encoding
- Supports software encoding
- Supports streaming to multiple clients
- Web UI for configuration

1.2 Integrations

1.3 Support

1.4 Downloads

CHAPTER

TWO

INSTALLATION

The recommended method for running Sunshine is to use the binaries bundled with the latest release.

2.1 Binaries

Binaries of Sunshine are created for each release. They are available for Linux, and Windows. Binaries can be found in the latest release.

Todo: Create binary package(s) for MacOS. See here.

Tip: Some third party packages also exist. See *Third Party Packages*.

2.2 Docker

Todo: Docker images of Sunshine are planned to be included in the future. They will be available on Dockerhub.io and ghcr.io.

2.3 Linux

Follow the instructions for your preferred package type below.

2.3.1 Applmage

The current known compatibility of the AppImage is shown below.

- [x] Debian oldstable (buster)
- [✓] Debian stable (bullseye)
- [✓] Debian testing (bookworm)
- [✓] Debian unstable (sid)

- [✓] Ubuntu jammy
- [✓] Ubuntu impish
- [✓] Ubuntu focal
- [x] Ubuntu bionic
- [x] Ubuntu xenial
- [x] Ubuntu trusty
- [x] CentOS 7
- 1. Download and extract sunshine-appimage.zip to your home directory.

2.3.2 Debian Packages

1. Download sunshine.deb and run the following code.

```
sudo apt install -f ./sunshine.deb
```

Tip: You can double click the deb file to see details about the package and begin installation.

2.3.3 Red Hat Packages

1. Add *rpmfusion* repositories by running the following code.

```
sudo dnf install https://mirrors.rpmfusion.org/free/fedora/rpmfusion-free-release-
→$(rpm -E %fedora).noarch.rpm \
https://mirrors.rpmfusion.org/nonfree/fedora/rpmfusion-nonfree-release-$(rpm -E
→%fedora).noarch.rpm
```

2. Download sunshine.rpm and run the following code.

```
sudo dnf install ./sunshine.rpm
```

Tip: You can double click the rpm file to see details about the package and begin installation.

2.4 MacOS

Portfile

- 1. Install MacPorts
- 2. Update the Macports sources.

```
sudo nano /opt/local/etc/macports/sources.conf
```

Add this line, replacing your username, below the line that starts with rsync.

file://Users/<username>/ports

Ctrl+x, then Y to exit and save changes.

3. Download the Portfile to ~/Downloads and run the following code.

```
mkdir -p ~/ports/multimedia/sunshine
mv ~/Downlaods/Portfile ~/ports/multimedia/sunshine
cd ~/ports
portindex
sudo port install sunshine
```

4. The first time you start Sunshine, you will be asked to grant access to screen recording and your microphone.

2.5 Windows

Installed option:

1. Download and install sunshine-windows.exe

Standalone option:

1. Download and extract sunshine-windows.zip

Todo: This is a planned feature. Currently no Dockerfile or image exists for Sunshine.

2.5. Windows 7

CHAPTER

THREE

DOCKER

3.1 Using docker run

Create and run the container (substitute your <values>):

```
docker run -d \
  --name=sunshine \
  --restart=unless-stopped
 -v <path to data>:/config \
 -e PUID=<uid> \
  -e PGID=<gid> \
 -e TZ=<timezone> \
  -p 47990:47990 \
  -p 47984:47984 \
  -p 47989:47989 \
  -p 48010:48010 \
  -p 47998:47998 \
  -p 47999:47999 \
  -p 48000:48000 \
  -p 48002:48002 \
  -p 48010:48010 \
  sunshinestream/sunshine
```

To update the container it must be removed and recreated:

```
# Stop the container
docker stop sunshine
# Remove the container
docker rm sunshine
# Pull the latest update
docker pull sunshinestream/sunshine
# Run the container with the same parameters as before
docker run -d ...
```

3.2 Using docker-compose

Create a docker-compose.yml file with the following contents (substitute your <values>):

```
version: '3'
services:
  sunshine:
    image: sunshinestream/sunshine
    container_name: sunshine
    restart: unless-stopped
    volumes:
    - <path to data>:/config
    environment:
    - PUID=<uid>
    - PGID=<qid>
    - TZ=<timezone>
    ports:
    - "47990:47990"
    - "47984:47984"
    - "47989:47989"
    - "48010:48010"
    - "47998:47998"
    - "47999:47999"
    - "48000:48000"
    - "48002:48002"
    - "48010:48010"
```

Create and start the container (run the command from the same folder as your docker-compose.yml file):

```
docker-compose up -d
```

To update the container:

```
# Pull the latest update
docker-compose pull
# Update and restart the container
docker-compose up -d
```

3.3 Parameters

You must substitute the <values> with your own settings.

Parameters are split into two halves separated by a colon. The left side represents the host and the right side the container.

Example: -p external:internal - This shows the port mapping from internal to external of the container. Therefore -p 47990:47990 would expose port 47990 from inside the container to be accessible from the host's IP on port 47990 (e.g. http://<host_ip>:47990). The internal port must be 47990, but the external port may be changed (e.g. -p 8080:47990).

10 Chapter 3. Docker

Parameter	Function	Example Value	Required
-p <port>:47990</port>	Web UI Port	47990	True
<pre>-v <path data="" to="">:/config</path></pre>	Volume mapping	/home/sunshine	True
-e PUID= <uid></uid>	User ID	1001	False
-e PGID= <gid></gid>	Group ID	1001	False
-e TZ= <timezone></timezone>	Lookup TZ value here	America/New_York	True

3.3.1 User / Group Identifiers:

When using data volumes (-v flags) permissions issues can arise between the host OS and the container. To avoid this issue you can specify the user PUID and group PGID. Ensure the data volume directory on the host is owned by the same user you specify.

In this instance PUID=1001 and PGID=1001. To find yours use id user as below:

```
$ id dockeruser
uid=1001(dockeruser) gid=1001(dockergroup) groups=1001(dockergroup)
```

3.3. Parameters 11

12 Chapter 3. Docker

CHAPTER

FOUR

THIRD PARTY PACKAGES

Danger: These packages are not maintained by SunshineStream. Use at your own risk.

4.1 AUR (Arch Linux User Repository)

4.2 Chocolatey

4.3 Scoop

4.4 Legacy GitHub Repo

Attention: This repo is not maintained. Thank you to Loki for bringing this amazing project to life!

CHAPTER

FIVE

USAGE

- 1. See the *setup* section for your specific OS.
- 2. Run sunshine <directory of conf file>/sunshine.conf.

Note: You do not need to specify a config file. If no config file is entered the default location will be used.

Attention: The configuration file specified will be created if it doesn't exist.

Tip: If using the Linux AppImage, replace sunshine with ./sunshine.AppImage

3. Configure Sunshine in the web ui The web ui is available on https://localhost:47990 by default. You may replace *localhost* with your internal ip address.

Attention: Ignore any warning given by your browser about "insecure website".

Caution: If running for the first time, make sure to note the username and password Sunshine showed to you, since you cannot get back later!

Add games and applications. This can be configured in the web ui.

Note: Additionally, apps can be configured manually. $src_assets/<os>/config/apps.json$ is an example of a list of applications that are started just before running a stream. This is the directory within the GitHub repo.

Attention: Application list is not fully supported on MacOS

- 4. In Moonlight, you may need to add the PC manually.
- 5. When Moonlight request you insert the correct pin on sunshine:
 - Login to the web ui
 - Go to "PIN" in the Header

- Type in your PIN and press Enter, you should get a Success Message
- In Moonlight, select one of the Applications listed

5.1 Network

Sunshine will be available on port 47990 by default.

Danger: Do not expose port 47990, or the web ui, to the internet!

5.2 Arguments

To get a list of available arguments run the following:

```
sunshine --help
```

5.3 Setup

5.3.1 Linux

The deb and rpm packages handle these steps automatically. The AppImage does not, third party packages may not as well.

Sunshine needs access to *uinput* to create mouse and gamepad events.

Add user to group input, if this is the first time installing.

```
sudo usermod -a -G input $USER sudo reboot now
```

Create udev rules.

```
sudo nano /etc/udev/rules.d/85-sunshine-input.rules
```

Input the following contents.

```
KERNEL=="uinput", GROUP="input", MODE="0660", OPTIONS+="static_node=uinput"
```

Save the file and exit:

- 1. CTRL+X to start exit.
- 2. Y to save modifications.

Configure autostart service

- filename: ~/.config/systemd/user/sunshine.service
- contents:

16 Chapter 5. Usage

[Unit]

Description=Sunshine Gamestream Server for Moonlight

[Service]

ExecStart=<see table>

[Install]

 ${\tt WantedBy=graphical-session.target}$

package	ExecStart	Auto Configured
deb	/usr/bin/sunshine	✓
rpm	/usr/bin/sunshine	✓
AppImage	~/sunshine.AppImage	×

Start once

systemctl --user start sunshine

Start on boot

systemctl --user enable sunshine

Additional Setup for KMS

Note: cap_sys_admin may as well be root, except you don't need to be root to run it. It is necessary to allow Sunshine to use KMS.

Enable

```
sudo setcap cap_sys_admin+p $(readlink -f $(which sunshine))
```

Disable

sudo setcap -r \$(readlink -f \$(which sunshine))

5.3.2 MacOS

Sunshine can only access microphones on macOS due to system limitations. To stream system audio use Soundflower or BlackHole and select their sink as audio device in *sunshine.conf*.

Note: Command Keys are not forwarded by Moonlight. Right Option-Key is mapped to CMD-Key.

Caution: Gamepads are not currently supported.

Configure autostart service

MacPorts

5.3. Setup 17

```
sudo port load Sunshine
```

5.3.3 Windows

For gamepad support, install ViGEmBus

5.4 Shortcuts

All shortcuts start with CTRL + ALT + SHIFT, just like Moonlight

- CTRL + ALT + SHIFT + N Hide/Unhide the cursor (This may be useful for Remote Desktop Mode for Moonlight)
- CTRL + ALT + SHIFT + F1/F13 Switch to different monitor for Streaming

5.5 Application List

- You can use Environment variables in place of values
- \$(HOME) will be replaced by the value of \$HOME
- \$\$ will be replaced by \$, e.g. \$\$(HOME) will be replaced by \$(HOME)
- env Adds or overwrites Environment variables for the commands/applications run by Sunshine
- "Variable name": "Variable value"
- apps The list of applications
- Example application:

- name The name of the application/game
- output The file where the output of the command is stored
- detached A list of commands to be run and forgotten about
- prep-cmd A list of commands to be run before/after the application
 - * If any of the prep-commands fail, starting the application is aborted

18 Chapter 5. Usage

- * do Run before the application
 - · If it fails, all undo commands of the previously succeeded do commands are run
- * undo Run after the application has terminated
 - · This should not fail considering it is supposed to undo the do commands
 - · If it fails, Sunshine is terminated
- * cmd The main application
 - · If not specified, a process is started that sleeps indefinitely

5.6 Considerations

- When an application is started, if there is an application already running, it will be terminated.
- When the application has been shutdown, the stream shuts down as well.
- In addition to the apps listed, one app "Desktop" is hardcoded into Sunshine. It does not start an application, instead it simply starts a stream.

5.6. Considerations

20 Chapter 5. Usage

CHAPTER

SIX

ADVANCED USAGE

Sunshine will work with the default settings for most users. In some cases you may want to configure Sunshine further.

6.1 Configuration

The default location for the configuration file is listed below. You can use another location if you choose, by passing in the full configuration file path as the first argument when you start Sunshine.

The default location of the apps.json is the same as the configuration file. You can use a custom location by modifying the configuration file.

Default File Location

Value	Description
Docker	/config/
Linux	/usr/local/sunshine/config/
MacOS	/usr/local/sunshine/config/
Windows	./config/

Example

sunshine ~/sunshine_config.conf

To manually configure sunshine you may edit the *conf* file in a text editor. Use the examples as reference.

Hint: Some settings are not available within the web ui.

6.2 General

6.2.1 sunshine name

Description The name displayed by Moonlight

Default PC hostname

Example

sunshine_name = Sunshine

6.2.2 min_log_level

Description The minimum log level printed to standard out.

Choices

Value	Description
verbose	verbose logging
debug	debug logging
info	info logging
warning	warning logging
error	error logging
fatal	fatal logging
none	no logging

Default info

Example

min_log_level = info

6.3 Controls

6.3.1 gamepad

Description The type of gamepad to emulate on the host.

Caution: Applies to Windows only.

Choices

Value	Description
x360	xbox 360 controller
ds4	dualshock controller (PS4)

Default x360

Example

gamepad = x360

6.3.2 back_button_timeout

Description If, after the timeout, the back/select button is still pressed down, Home/Guide button press is emulated. On Nvidia Shield, the home and power button are not passed to Moonlight.

Tip: If back_button_timeout < 0, then the Home/Guide button will not be emulated.

Default 2000

Example

```
back_button_timeout = 2000
```

6.3.3 key_repeat_delay

Description The initial delay in milliseconds before repeating keys. Controls how fast keys will repeat themselves.

Default 500

Example

```
key_repeat_delay = 500
```

6.3.4 key_repeat_frequency

Description How often keys repeat every second.

Tip: This configurable option supports decimals.

Default

Todo: Unknown

Example

```
key_repeat_frequency = 24.9
```

6.3.5 keybindings

Description Sometimes it may be useful to map keybindings. Wayland won't allow clients to capture the Win Key for example.

```
Tip: See virtual key codes
```

Hint: keybindings needs to have a multiple of two elements.

Default None

Example

```
keybindings = [
    0x10, 0xA0,
    0x11, 0xA2,
    0x12, 0xA4,
    0x4A, 0x4B
]
```

6.3. Controls 23

6.3.6 key_rightalt_to_key_win

Description It may be possible that you cannot send the Windows Key from Moonlight directly. In those cases it may be useful to make Sunshine think the Right Alt key is the Windows key.

Default None

Example

```
key_rightalt_to_key_win = enabled
```

6.4 Display

6.4.1 adapter name

Description Select the video card you want to stream.

Tip: To find the name of the appropriate values follow these instructions.

Linux + VA-API Unlike with amdvce and nvenc, it doesn't matter if video encoding is done on a different GPU.

To be supported by Sunshine, it needs to have at the very minimum: VAProfileH264High: VAEntrypointEncSlice

Todo: MacOS

Windows

```
tools\dxgi-info.exe
```

Default Sunshine will select the default video card.

Examples

Linux

```
adapter_name = /dev/dri/renderD128
```

Todo: MacOS

Windows

```
adapter_name = Radeon RX 580 Series
```

6.4.2 output_name

Description Select the display number you want to stream.

Tip: To find the name of the appropriate values follow these instructions.

Linux

```
xrandr --listmonitors
```

Example output: 0: +HDMI-1 1920/518x1200/324+0+0 HDMI-1

You need to use the value before the colon in the output, e.g. 0.

Todo: MacOS

Windows

```
tools\dxgi-info.exe
```

Default Sunshine will select the default display.

Examples

Linux

```
output\_name = 0
```

Todo: MacOS

Windows

```
output_name = \\.\DISPLAY1
```

6.4.3 fps

Description The fps modes advertised by Sunshine.

Note: Some versions of Moonlight, such as Moonlight-nx (Switch), rely on this list to ensure that the requested fps is supported.

Default

Todo: Unknown

6.4. Display 25

Example

```
fps = [10, 30, 60, 90, 120]
```

6.4.4 resolutions

Description The resolutions advertised by Sunshine.

Note: Some versions of Moonlight, such as Moonlight-nx (Switch), rely on this list to ensure that the requested resolution is supported.

Default

Todo: Unknown

Example

```
resolutions = [
    352x240,
    480x360,
    858x480,
    1280x720,
    1920x1080,
    2560x1080,
    3440x1440,
    1920x1200,
    3860x2160,
    3840x1600,
]
```

6.4.5 dwmflush

Description Invoke DwmFlush() to sync screen capture to the Windows presentation interval.

Caution: Applies to Windows only. Alleviates visual stuttering during mouse movement. If enabled, this feature will automatically deactivate if the client framerate exceeds the host monitor's current refresh rate.

Default enabled

Examples

Windows

```
dwmflush = enabled
```

6.5 Audio

6.5.1 audio_sink

Description The name of the audio sink used for audio loopback.

Tip: To find the name of the audio sink follow these instructions.

Linux + pulseaudio

```
pacmd list-sinks | grep "name:"
```

Linux + pipewire

```
pactl info | grep Source
# in some causes you'd need to use the `Sink` device, if `Source` doesn't work, source try:
pactl info | grep Sink
```

MacOS Sunshine can only access microphones on MacOS due to system limitations. To stream system audio use Soundflower or BlackHole.

Windows

```
tools\audio-info.exe
```

Default Sunshine will select the default audio device.

Examples

Linux

```
audio_sink = alsa_output.pci-0000_09_00.3.analog-stereo
```

MacOS

```
audio_sink = BlackHole 2ch
```

Windows

```
audio_sink = {0.0.0.00000000}.{FD47D9CC-4218-4135-9CE2-0C195C87405B}
```

6.5.2 virtual_sink

Description The audio device that's virtual, like Steam Streaming Speakers. This allows Sunshine to stream audio, while muting the speakers.

Tip: See *audio_sink*!

Default

6.5. Audio 27

Todo: Unknown

Example

```
virtual_sink = {0.0.0.00000000}.{8edba70c-1125-467c-b89c-15da389bc1d4}
```

6.6 Network

6.6.1 external_ip

Description If no external IP address is given, Sunshine will attempt to automatically detect external ip-address.

Default Automatic

Example

```
external_ip = 123.456.789.12
```

6.6.2 port

Description Set the family of ports used by Sunshine.

Default 47989

Example

```
port = 47989
```

6.6.3 pkey

Description The private key. This must be 2048 bits.

Default

Todo: Unknown

Example

```
pkey = /dir/pkey.pem
```

6.6.4 cert

Description The certificate. Must be signed with a 2048 bit key.

Default

Todo: Unknown

Example

```
cert = /dir/cert.pem
```

6.6.5 origin_pin_allowed

Description The origin of the remote endpoint address that is not denied for HTTP method /pin.

Choices

Value	Description
pc	Only localhost may access /pin
lan	Only LAN devices may access /pin
wan	Anyone may access /pin

Default pc

Example

```
origin_pin_allowed = pc
```

6.6.6 origin_web_ui_allowed

Description The origin of the remote endpoint address that is not denied for HTTPS Web UI.

Choices

Value	Description
pc	Only localhost may access the web ui
lan	Only LAN devices may access the web ui
wan	Anyone may access the web ui

Default lan

Example

```
origin_web_ui_allowed = lan
```

6.6. Network

6.6.7 upnp

Description Sunshine will attempt to open ports for streaming over the internet.

Choices

Value	Description
on	enable UPnP
off	disable UPnP

Default off

Example

```
upnp = on
```

6.6.8 ping timeout

Description How long to wait in milliseconds for data from Moonlight before shutting down the stream.

Default 10000

Example

ping_timeout = 10000

6.7 Encoding

6.7.1 channels

Description This will generate distinct video streams, unlike simply broadcasting to multiple Clients.

When multicasting, it could be useful to have different configurations for each connected Client.

For instance:

- Clients connected through WAN and LAN have different bitrate constraints.
- Decoders may require different settings for color.

Warning: CPU usage increases for each distinct video stream generated.

Default 1

Example

channels = 1

6.7.2 fec_percentage

Description Percentage of error correcting packets per data packet in each video frame.

Warning: Higher values can correct for more network packet loss, but at the cost of increasing bandwidth usage.

Default 20

Range 1-255

Example

```
fec_percentage = 20
```

6.7.3 qp

Description Quantitization Parameter. Some devices don't support Constant Bit Rate. For those devices, QP is used instead.

Warning: Higher value means more compression, but less quality.

Default 28

Example

```
qp = 28
```

6.7.4 min_threads

Description Minimum number of threads used by ffmpeg to encode the video.

Note: Increasing the value slightly reduces encoding efficiency, but the tradeoff is usually worth it to gain the use of more CPU cores for encoding. The ideal value is the lowest value that can reliably encode at your desired streaming settings on your hardware.

Default 1

Example

```
min_{threads} = 1
```

6.7. Encoding 31

6.7.5 hevc mode

Description Allows the client to request HEVC Main or HEVC Main10 video streams.

Warning: HEVC is more CPU-intensive to encode, so enabling this may reduce performance when using software encoding.

Choices

Value	Description
0	advertise support for HEVC based on encoder
1	do not advertise support for HEVC
2	advertise support for HEVC Main profile
3	advertise support for HEVC Main and Main10 (HDR) profiles

Default 0

Example

```
hevc_mode = 2
```

6.7.6 encoder

Description Force a specific encoder.

Choices

Value	Description
nvenc	For Nvidia graphics cards
amdvce	For AMD graphics cards
software	Encoding occurs on the CPU

Default Sunshine will use the first encoder that is available.

Example

```
encoder = nvenc
```

6.7.7 sw preset

Description The encoder preset to use.

Note: This option only applies when using software *encoder*.

Note: From FFmpeg.

A preset is a collection of options that will provide a certain encoding speed to compression ratio. A slower preset will provide better compression (compression is quality per filesize). This means that, for example, if you target a certain file size or constant bit rate, you will achieve better quality with a slower preset. Similarly, for constant quality encoding, you will simply save bitrate by choosing a slower preset.

Use the slowest preset that you have patience for.

Choices

Value	Description
ultrafast	fastest
superfast	
veryfast	
superfast	
faster	
fast	
medium	
slow	
slow	
slower	
veryslow	slowest

Default superfast

Example

sw_preset = superfast

6.7.8 sw_tune

Description The tuning preset to use.

Note: This option only applies when using software *encoder*.

Note: From FFmpeg.

You can optionally use -tune to change settings based upon the specifics of your input.

Choices

Value	Description
film	use for high quality movie content; lowers deblocking
animation	good for cartoons; uses higher deblocking and more reference frames
grain	preserves the grain structure in old, grainy film material
stillimage	good for slideshow-like content
fastdecode	allows faster decoding by disabling certain filters
zerolatency	good for fast encoding and low-latency streaming

Default zerolatency

Example

sw_tune = zerolatency

6.7. Encoding 33

6.7.9 nv_preset

Description The encoder preset to use.

Note: This option only applies when using nvenc *encoder*.

Choices

Value	Description
default	let ffmpeg decide
hp	high performance
hq	high quality
slow	high quality, 2 passes
medium	high quality, 1 pass
fast	high performance, 1 pass
bd	
11	low latency
llhq	low latency, high quality
llhp	low latency, high performance
lossless	lossless
losslesshp	lossless, high performance

Default 11hq

Example

nv_preset = llhq

6.7.10 nv_rc

Description The encoder rate control.

Note: This option only applies when using nvenc *encoder*.

Note: Moonlight does not currently support variable bitrate, although it can still be selected here.

Choices

Value	Description
auto	let ffmpeg decide
constqp	constant QP mode
cbr	constant bitrate
cbr_hq	constant bitrate, high quality
cbr_ld_hq	constant bitrate, low delay, high quality
vbr	variable bitrate
vbr_hq	variable bitrate, high quality

Default auto

Example

```
nv_rc = auto
```

6.7.11 nv_coder

Description The entropy encoding to use.

Note: This option only applies when using nvenc *encoder*.

Choices

Value	Description
auto	let ffmpeg decide
cabac	
cavlc	

Default auto

Example

nv_coder = auto

6.7.12 amd_quality

Description The encoder preset to use.

Note: This option only applies when using amdvce *encoder*.

Choices

Value	Description
default	let ffmpeg decide
speed	fast
balanced	balance performance and speed

Default balanced

Example

amd_quality = balanced

6.7. Encoding 35

6.7.13 amd_rc

Description The encoder rate control.

Note: This option only applies when using amdvce *encoder*.

Note: Moonlight does not currently support variable bitrate, although it can still be selected here.

Choices

Value	Description
auto	let ffmpeg decide
constqp	constant QP mode
cbr	constant bitrate
vbr_latency	variable bitrate, latency constrained
vbr_peak	variable bitrate, peak constrained

Default auto

Example

 $amd_rc = auto$

6.7.14 amd_coder

Description The entropy encoding to use.

Note: This option only applies when using nvenc *encoder*.

Choices

Value	Description
auto	let ffmpeg decide
cabac	
cavlc	

Default auto

Example

amd_coder = auto

6.7.15 vt_software

Description Force Video Toolbox to use software encoding.

Note: This option only applies when using MacOS.

Choices

Value	Description
auto	let ffmpeg decide
disabled	disable software encoding
allowed	allow software encoding
forced	force software encoding

Default auto

Example

vt_software = auto

6.7.16 vt_realtime

Description Realtime encoding.

Note: This option only applies when using MacOS.

Warning: Disabling realtime encoding might result in a delayed frame encoding or frame drop.

Default enabled

Example

vt_realtime = enabled

6.7.17 vt_coder

Description The entropy encoding to use.

Note: This option only applies when using MacOS.

Choices

Value	Description
auto	let ffmpeg decide
cabac	
cavlc	

Default auto

6.7. Encoding 37

Example

```
vt_coder = auto
```

6.8 Advanced

6.8.1 file_apps

Description The application configuration file path. The file contains a json formatted list of applications that can be started by Moonlight.

Default OS and package dependent

Example

```
file_apps = apps.json
```

6.8.2 file_state

Description The file where current state of Sunshine is stored.

Default sunshine_state.json

Example

```
file_state = sunshine_state.json
```

6.8.3 credentials_file

Description The file where user credentials for the UI are stored.

Default sunshine_state.json

Example

```
credentials_file = sunshine_state.json
```

SEVEN

GENERAL

If you forgot your credentials to the web UI, try this.

sunshine -creds <new username> <new password>

Can't access the web UI?

1. Check firefall rules.

40 Chapter 7. General

EIGHT

LINUX

If screencasting fails with Wayland, you may need to run the following to force screencasting with X11.

sudo setcap -r \$(readlink -f \$(which sunshine))

42 Chapter 8. Linux

NINE

MACOS

If you get this error:

Dynamic session lookup supported but failed: launchd did not provide a socket path, verify that org.freedesktop.dbus-session.plist is loaded!

Try this.

 $\label{load-w} \mbox{${\tt launchAgents/org.freedesktop.dbus-session.}$} $$ \hookrightarrow \mbox{${\tt plist}$} $$$

Chapter 9. MacOS

CHAPTER TEN

WINDOWS

No gamepad is detected.

1. Verify that you've installed ViGEmBus.

ELEVEN

BUILD

Sunshine binaries are built using CMake. Cross compilation is not supported. That means the binaries must be built on the target operating system and architecture.

11.1 Building Locally

11.1.1 Clone

Ensure git is installed and run the following:

git clone https://github.com/sunshinestream/sunshine.git --recurse-submodules cd sunshine && mkdir build && cd build

11.1.2 Compile

See the section specific to your OS.

- Linux
- MacOS
- Windows

11.2 Remote Build

It may be beneficial to build remotely in some cases. This will enable easier building on different operating systems.

- 1. Fork the project
- 2. Activate workflows
- 3. Trigger the CI workflow manually
- 4. Download the artifacts/binaries from the workflow run summary

48 Chapter 11. Build

TWELVE

LINUX

12.1 Requirements

Danger: Installing these dependencies may break your distribution. It is recommended to build in a virtual machine or to use the *Dockerfile builds* located in the *./scripts* directory.

12.1.1 Debian Bullseye

End of Life: TBD

Install Requirements

```
sudo apt update && sudo apt install \
   build-essential \
   cmake \
   git \
   libavdevice-dev \
   libboost-filesystem-dev \
   libboost-log-dev \
   libboost-thread-dev \
   libcap-dev \ # KMS
   libdrm-dev \ # KMS
   libevdev-dev \
   libpulse-dev \
   libopus-dev \
   libssl-dev \
   libwayland-dev \ # Wayland
   libx11-dev \ # X11
   libxcb-shm0-dev \ # X11
   libxcb-xfixes0-dev \ # X11
   libxcb1-dev \ # X11
   libxfixes-dev \ # X11
   libxrandr-dev \ # X11
   libxtst-dev \ # X11
   nvidia-cuda-dev \ # Cuda, NvFBC
   nvidia-cuda-toolkit \ # Cuda, NvFBC
```

12.1.2 Fedora 35

End of Life: TBD

Install Repositories

```
sudo dnf update && \
    sudo dnf group install "Development Tools" && \
    sudo dnf install https://mirrors.rpmfusion.org/free/fedora/rpmfusion-free-
    →release-$(rpm -E %fedora).noarch.rpm https://mirrors.rpmfusion.org/nonfree/fedora/
    →rpmfusion-nonfree-release-$(rpm -E %fedora).noarch.rpm
```

Install Requirements

```
sudo dnf install \
   boost-devel \
   boost-static.x86_64 \
   cmake \
   ffmpeg-devel \
   gcc-c++ \
   libevdev-devel \
   libX11-devel \ # X11
   libxcb-devel \ # X11
   libXcursor-devel \ # X11
   libXfixes-devel \ # X11
   libXinerama-devel \ # X11
   libXi-devel \ # X11
   libXrandr-devel \ # X11
   libXtst-devel \ # X11
   mesa-libGL-devel \
   openssl-devel \
   opus-devel \
   pulseaudio-libs-devel \
   rpm-build \ # if you want to build an RPM binary package
```

12.1.3 Ubuntu 18.04

End of Life: April 2028

Install Repositories

```
sudo apt update && sudo apt install \
    software-properties-common \
    && add-apt-repository ppa:savoury1/graphics && \
    add-apt-repository ppa:savoury1/multimedia && \
    add-apt-repository ppa:savoury1/ffmpeg4 && \
    add-apt-repository ppa:savoury1/boost-defaults-1.71 && \
    add-apt-repository ppa:ubuntu-toolchain-r/test && \
```

Install Requirements

```
sudo apt install \
   build-essential \
   cmake \
   (continues on next page)
```

50 Chapter 12. Linux

(continued from previous page)

```
gcc-10 \
git \
g++-10 \
libavdevice-dev \
libboost-filesystem1.71-dev \
libboost-log1.71-dev \
libboost-regex1.71-dev \
libboost-thread1.71-dev \
libcap-dev \ # KMS
libdrm-dev \ # KMS
libevdev-dev \
libpulse-dev \
libopus-dev \
libssl-dev \
libwayland-dev \ # Wayland
libx11-dev \ # X11
libxcb-shm0-dev \ # X11
libxcb-xfixes0-dev \ # X11
libxcb1-dev \ # X11
libxfixes-dev \ # X11
libxrandr-dev \ # X11
libxtst-dev \ # X11
wget \
```

Update gcc alias

```
update-alternatives --install /usr/bin/gcc gcc /usr/bin/gcc-10 100 --slave /usr/bin/ _{\to g++} g++ /usr/bin/g++-10
```

Install CuDA

```
wget https://developer.download.nvidia.com/compute/cuda/11.4.2/local_installers/

cuda_11.4.2_470.57.02_linux.run --progress=bar:force:noscroll -q --show-progress -

0 ./cuda.run && chmod a+x ./cuda.run

./cuda.run --silent --toolkit --toolkitpath=/usr --no-opengl-libs --no-man-page --

cupo-drm && rm ./cuda.run
```

Install CMake

```
wget https://cmake.org/files/v3.22/cmake-3.22.2-linux-x86_64.sh
mkdir /opt/cmake
sh /cmake-3.22.2-linux-x86_64.sh --prefix=/opt/cmake --skip-license
ln -s /opt/cmake/bin/cmake /usr/local/bin/cmake
cmake --version
```

12.1. Requirements 51

12.1.4 Ubuntu 20.04

End of Life: April 2030

Install Requirements

```
sudo apt update && sudo apt install \
   build-essential \
   cmake \
   git \
   libavdevice-dev \
   libboost-filesystem-dev \
   libboost-log-dev \
   libboost-thread-dev \
   libcap-dev \ # KMS
   libdrm-dev \ # KMS
   libevdev-dev \
   libpulse-dev \
   libopus-dev \
   libssl-dev \
   libwayland-dev \ # Wayland
   libx11-dev \ # X11
   libxcb-shm0-dev \ # X11
   libxcb-xfixes0-dev \ # X11
   libxcb1-dev \ # X11
   libxfixes-dev \ # X11
   libxrandr-dev \ # X11
   libxtst-dev \ # X11
   wget \
```

Update gcc alias

```
update-alternatives --install /usr/bin/gcc gcc /usr/bin/gcc-10 100 --slave /usr/bin/ _{
m \hookrightarrow}g++ g++ /usr/bin/g++-10
```

Install CuDA

```
wget https://developer.download.nvidia.com/compute/cuda/11.4.2/local_installers/
→cuda_11.4.2_470.57.02_linux.run --progress=bar:force:noscroll -q --show-progress -
→0 ./cuda.run && chmod a+x ./cuda.run
./cuda.run --silent --toolkit --toolkitpath=/usr --no-opengl-libs --no-man-page --
→no-drm && rm ./cuda.run
```

12.1.5 Ubuntu 21.10

End of Life: July 2022

Install Requirements

```
sudo apt update && sudo apt install \
   build-essential \
   cmake \
   git \
```

(continues on next page)

52 Chapter 12. Linux

(continued from previous page)

```
libavdevice-dev \
libboost-filesystem-dev \
libboost-log-dev \
libboost-thread-dev \
libcap-dev \ # KMS
libdrm-dev \ # KMS
libevdev-dev \
libpulse-dev \
libopus-dev \
libssl-dev \
libwayland-dev \ # Wayland
libx11-dev \ # X11
libxcb-shm0-dev \ # X11
libxcb-xfixes0-dev \ # X11
libxcb1-dev \ # X11
libxfixes-dev \ # X11
libxrandr-dev \ # X11
libxtst-dev \ # X11
nvidia-cuda-dev \ # Cuda, NvFBC
nvidia-cuda-toolkit \ # Cuda, NvFBC
```

12.1.6 Ubuntu 22.04

End of Life: April 2027

Todo: Create Ubuntu 22.04 Dockerfile and complete this documentation.

12.2 Build

Attention: Ensure you are in the build directory created during the clone step earlier before continuing.

Debian based OSes

```
cmake -DCMAKE_C_COMPILER=gcc-10 -DCMAKE_CXX_COMPILER=g++-10 ..
```

Red Hat based Oses

```
cmake -DCMAKE_C_COMPILER=gcc -DCMAKE_CXX_COMPILER=g++ ..
```

Finally

```
make -j ${nproc}
cpack -G DEB # optionally, create a deb package
cpack -G RPM # optionally, create a rpm package
```

12.2. Build 53

12.3 Dockerfile Builds

You may wish to simply build sunshine from source, without bloating your OS with development files. There are scripts located in the ./scripts directory that will create docker images that have the necessary packages. As a result, removing the development files after you're done is a single command away. These scripts use docker under the hood, as such, they can only be used to compile the Linux version

Todo: Publish the Dockerfiles to Dockerhub and ghcr.

Requirements Install Docker

Instructions

- 1. Clone. Sunshine.
- 2. Select the desired Dockerfile from the ./scripts directory.

Available Files:

```
Dockerfile-debian
Dockerfile-fedora_33  # end of life
Dockerfile-fedora_35
Dockerfile-ubuntu_18_04
Dockerfile-ubuntu_20_04
Dockerfile-ubuntu_21_04  # end of life
Dockerfile-ubuntu_21_10
```

3. Execute

```
cd scripts # move to the scripts directory
./build-container.sh -f Dockerfile-<name> # create the container (replace the "

→<name>")
./build-sunshine.sh -p -s .. # compile and build sunshine
```

4. Updating

```
git pull # pull the latest changes from github
./build-sunshine.sh -p -s .. # compile and build sunshine
```

5. Optionally, delete the container .. code-block:: bash

./build-container.sh -c delete

6. Install the resulting package

Debian

```
sudo apt install -f sunshine-build/sunshine.deb
```

Red Hat

```
sudo dnf install sunshine-build/sunshine.rpm
```

54 Chapter 12. Linux

THIRTEEN

MACOS

13.1 Requirements

MacOS Big Sur and Xcode 12.5+ Use either MacPorts or Homebrew

13.1.1 MacPorts

Install Requirements

```
sudo port install cmake boost ffmpeg libopus
```

13.1.2 Homebrew

Install Requirements

```
brew install boost cmake ffmpeg opus
# if there are issues with an SSL header that is not found:
cd /usr/local/include
ln -s ../opt/openssl/include/openssl .
```

13.2 Build

```
Attention: Ensure you are in the build directory created during the clone step earlier before continuing.

cmake ..
make -j ${nproc}}

cpack -G DragNDrop # optionally, create a MacOS dmg package
```

If cmake fails complaining to find Boost, try to set the path explicitly.

```
\label{loss_make_def} $$\operatorname{DBOOST\_ROOT=[boost\ path]\ ..,\ e.g.,\ cmake\ -DBOOST\_ROOT=/opt/local/libexec/boost/1.76\ ..}$
```

56 Chapter 13. MacOS

FOURTEEN

WINDOWS

14.1 Requirements

First you need to install MSYS2, then startup "MSYS2 MinGW 64-bit" and install the following packages using:

```
pacman -S mingw-w64-x86_64-binutils mingw-w64-x86_64-openssl mingw-w64-x86_64-cmake<sub>→</sub> mingw-w64-x86_64-toolchain mingw-w64-x86_64-opus mingw-w64-x86_64-x265 mingw-w64-x86_ → 64-boost git mingw-w64-x86_64-make cmake make gcc
```

14.2 Build

```
Attention: Ensure you are in the build directory created during the clone step earlier before continuing.

Cmake -G"Unix Makefiles" .. # alternatively

mingw32-make

cpack -G NSIS # optionally, create a windows installer

cpack -G ZIP # optionally, create a windows standalone package
```

FIFTEEN

CONTRIBUTING

- 1. Fork the repo on GitHub
- 2. Create a new branch for the feature you are adding or the issue you are fixing

Tip: Base the new branch off the *nightly* branch. It will make your life easier when you submit the PR!

- 3. Make changes, push commits, etc.
- 4. Files should contain an empty line at the end.
- 5. Document your code!
- 6. Test your code!
- 7. When ready create a PR to this repo on the *nightly* branch.

Hint: If you accidentally make your PR against a different branch, a bot will comment letting you know it's on the wrong branch. Don't worry. You can edit the PR to change the target branch. There is no reason to close the PR!

Note: Draft PRs are also welcome as you work through issues. The benefit of creating a draft PR is that an automated build can run in a github runner.

Attention: Do not expect partially complete PRs to be merged. These topics will be considered before merging.

• Does the code follows the style guidelines of this project?

Tip: Look at examples of existing code in the project!


- Is the code well commented?
- Were documentation blocks updated for new or modified components?

Note: Developers and maintainers will attempt to assist with challenging issues.

SIXTEEN

LOCALIZATION

Sunshine is being localized into various languages. The default language is *en* (English) and is highlighted green.



Graph

16.1 Crowdln

The translations occur on CrowdIn. Feel free to contribute to localization there. Only elements of the API are planned to be translated.

Attention: The rest API has not yet been implemented.

Translations Basics

- The brand names *SunshineStream* and *Sunshine* should never be translated.
- Other brand names should never be translated. Examples:
 - AMD
 - Nvidia

CrowdIn Integration How does it work?

When a change is made to sunshine source code, a workflow generates new translation templates that get pushed to CrowdIn automatically.

When translations are updated on CrowdIn, a push gets made to the *l10n_nightly* branch and a PR is made against the *nightly* branch. Once PR is merged, all updated translations are part of the project and will be included in the next release.

16.2 Extraction

There should be minimal cases where strings need to be extracted from source code; however it may be necessary in some situations. For example if a system tray icon is added it should be localized as it is user interfacing.

• Wrap the string to be extracted in a function as shown.

```
#include <boost/locale.hpp>
boost::locale::translate("Hello world!")
```

Tip: More examples can be found in the documentation for boost locale.

Warning: This is for information only. Contributors should never include manually updated template files, or manually compiled language files in Pull Requests.

Strings are automatically extracted from the code to the *locale/sunshine.po* template file. The generated file is used by CrowdIn to generate language specific template files. The file is generated using the *.github/workflows/localize.yml* workflow and is run on any push event into the *nightly* branch. Jobs are only run if any of the following paths are modified.

```
- 'sunshine/**'
```

When testing locally it may be desirable to manually extract, initialize, update, and compile strings. Python is required for this, along with the python dependencies in the ./scripts/requirements.txt file. Additionally, xgettext must be installed.

Extract, initialize, and update

```
python ./scripts/_locale.py --extract --init --update
```

Compile

```
python ./scripts/_locale.py --compile
```

16.2. Extraction 63

SEVENTEEN

TESTING

17.1 Clang Format

Source code is tested against the .clang-format file for linting errors. The workflow file responsible for clang format testing is .github/workflows/clang.yml.

Test clang-format locally.

Todo: This documentation needs to be improved.

clang-format ...

17.2 Sphinx

Sunshine uses Sphinx for documentation building. Sphinx is included in the ./scripts/requirements.txt file. Python is required to build sphinx docs. Installation and setup of python will not be covered here.

The config file for Sphinx is docs/source/conf.py. This is already included in the repo and should not be modified.

Test with Sphinx

cd docs
make html

Alternatively

cd docs
sphinx-build -b html source build

17.3 Unit Testing

Todo: Sunshine does not currently have any unit tests. If you would like to help us improve please get in contact with us, or make a PR with suggested changes.

66 Chapter 17. Testing